(../../)

finstalling on Linux

For x86 systems.

- 1. In your browser, download the <u>Anaconda installer for Linux</u> (https://www.anaconda.com/download/#linux).
- 2. Optional: <u>Verify data integrity with MD5 or SHA-256 (../hashes/</u>). (For more information on hashes, see <u>cryptographic hash validation (https://conda.io/projects/conda/en/latest/user-guide/install/download.html#cryptographic-hash-verification</u>).)
 - a. Run the following:

```
md5sum /path/filename
```

OR:

sha256sum /path/filename

NOTE: Replace /path/filename with the actual path and filename of the file you downloaded.

- b. Optional: Verify results against <u>the proper hash page (../hashes/)</u> to make sure the hashes match.
- 3. Enter the following to install Anaconda for Python 3.7:

```
bash ~/Downloads/Anaconda3-5.3.0-Linux-x86_64.sh
```

OR Enter the following to install Anaconda for Python 2.7:

```
bash ~/Downloads/Anaconda2-5.3.0-Linux-x86_64.sh
```

NOTE: Include the bash command regardless of whether or not you are using Bash shell.

NOTE: If you did not download to your Downloads directory, replace ~/Downloads/ with the path to the file you downloaded.

NOTE: Choose "Install Anaconda as a user" unless root privileges are required.

- 4. The installer prompts "In order to continue the installation process, please review the license agreement." Click Enter to view license terms.
- 5. Scroll to the bottom of the license terms and enter "Yes" to agree.
- 6. The installer prompts you to click Enter to accept the default install location, CTRL-C to cancel the installation, or specify an alternate installation directory. If you accept the default install location, the installer displays "PREFIX=/home/<user>/anaconda<2 or 3>" and continues the installation. It may take a few minutes to complete.
- 7. The installer prompts "Do you wish the installer to prepend the Anaconda<2 or 3> install location to PATH in your /home/<user>/.bashrc ?" Enter Yes .
 - NOTE: If you enter "No", you must manually add the path to Anaconda or conda will not work. See <u>FAQ (../../user-guide/faq/#distribution-faq-linux-path)</u>.
- 8. The installer describes Microsoft VS Code and asks if you would like to install VS Code. Enter yes or no . If you selected yes , follow the instructions on screen to complete the VS Code installation.
 - NOTE: Installing VS Code with the Anaconda installer requires an internet connection. Offline users may be able to find an offline VS Code installer from Microsoft.
- 9. The installer finishes and displays "Thank you for installing Anaconda<2 or 3>!"
- 10. Close and open your terminal window for the installation to take effect, or you can enter the command source ~/.bashrc.
- 11. After your install is complete, verify it by opening Anaconda Navigator, a program that is included with Anaconda: Open a Terminal window and type anaconda-navigator. If Navigator opens, you have successfully installed Anaconda. If not, check that you completed each step above, then see our <u>Help page (./././reference/help-support/)</u>.
 - TIP: For more information about Anaconda Navigator, see Navigator (../../navigator/).

After your install completes, start using Anaconda with the instructions in <u>Getting started with Anaconda (../../user-guide/getting-started/)</u>.

NOTE: If you install multiple versions of Anaconda, the system defaults to the most current version, as long as you haven't altered the default install path.

« Installing on macOS (../mac-os/)

Installing on Linux POWER » (../linux-power8/)

Docs Home (../../)

Anaconda Home (https://www.anaconda.com/)

More Help & Support (https://www.anaconda.com/support)

© 2019 Anaconda, Inc. All Rights Reserved. Privacy Policy (https://www.anaconda.com/privacy-policy/)